



Voice Intelligent Technology

Integration Guide



Document information	
Title	VIT - Integration Guide
Status	
Version	1.5
Date	December 11, 2020
Author	S. Chereau
Reviewers	
Document ID	
Security	CONFIDENTIAL The attached material and the information contained therein are proprietary to NXP and are issued only under strict confidentiality arrangements. Without a separate written authorization, it shall not be used for any purpose whatsoever, reproduced, copied in whole or in part, adapted, modified, or disseminated. It must be returned to NXP upon its first request.
Usage	NXP

Change History

Version	Status	Description	Author	Date
1.0	REL	Creation	Sebastien Chereau	2019-11-29
1.1	REL	Updated with Voice Commands information	Sebastien Chereau	2020-06-30
1.2	REL	Adding VIT programming sequence	Sebastien Chereau	2020-08-07
1.3	REL	Updating profiling	Sebastien Chereau	2020-09-14
1.4	REL	Adding information on VIT_GetStatusParameters()	Sebastien Chereau	2020-11-12
1.5	REL	Updating RT600 information	Sebastien Chereau	2020-12-11



1	REFERENCE & ABBREVIATIONS	4
2	INTRODUCTION.....	5
3	RELEASE DESCRIPTION.....	6
4	PUBLIC INTERFACES DESCRIPTION.....	6
4.1	HEADER FILES	6
4.1.1	VIT.h	6
4.1.2	VIT_Model.h.....	7
4.1.3	PL_platformTypes_CortexM7.h.....	7
4.1.4	PL_platformTypes_HIFI4.h.....	7
4.1.5	PL_memoryRegion.h.....	7
4.2	PUBLIC APIS.....	7
4.2.1	Main APIS.....	8
4.2.1.1	VIT_SetModel.....	8
4.2.1.2	VIT_GetMemoryTable.....	8
4.2.1.3	VIT_GetInstanceHandle.....	9
4.2.1.4	VIT_SetControlParameters.....	10
4.2.1.5	VIT_Process.....	10
4.2.1.6	VIT_GetVoiceCommandFound	11
4.2.2	Secondary APIS.....	12
4.2.2.1	VIT_GetModelInfo.....	12
4.2.2.2	VIT_ResetInstance.....	12
4.2.2.3	VIT_GetControlParameters.....	13
4.2.2.4	GET_StatusParameters.....	14
4.3	PROGRAMMING SEQUENCE	14
4.4	CODE SAMPLE.....	16
4.4.1	Initialization phase.....	16
4.4.2	Process phase.....	17
4.4.3	Delete phase.....	18
4.4.4	Additional code snippet (secondary APIs)	19
5	VIT PROFILING	20
6	APPENDIX.....	21



1 Reference & Abbreviations

References	
[1]	Release Notes

Table 1: Reference documents

Abbreviations	
VIT	Voice Intelligent Technology
WWE	Wake Word Engine
VCE	Voice Commands Engine

Table 2: Abbreviations

2 Introduction

Voice Intelligent Technology product is providing Voice services aiming to wake up and control IOT, Home devices.

Current version of VIT is supporting a Wake Word and a Voice Commands Text2Model functionalities.




Figure 1 : VIT overview

The WakeWord model is built from a Database with recorded "keyword" files.

The Voice Commands Model is built from a text2Model approach which does not require any Command audio dataset.

The VIT lib is provided with a model allowing the detection of the "Hey NXP" key word and 12 Commands listed in VIT_Voice_Commands.h file.

Scenario supported by the VIT LIB :

- Wake Word detection only : "Hey NXP"



- WakeWord + Voice Commands detection
Eg “Hey NXP – Play Music” - “Hey NXP – Next”

The Voice command should be pronounced in a 3 seconds time frame after the Wake word. See Appendix section for further details.

VIT will return an “UNKOWN” command if the audio captured after the WakeWord does not correspond to any targeted command.

The VIT lib is processing 10ms audio frame @16kHz - 16-bit data - mono

The VIT Lib has been ported on 2 cores :

- The VIT lib has been built for cortex-M7 core and validated on the IMXRT1060 platform.
- The VIT lib has been built for HIFI4 core and validated on the Xtensa simulator.

The VIT release is aimed to be distributed only for demo or evaluation purpose.

3 Release description

The VIT release is including following files :

- Lib/libVIT_PLATFORM_VERSION.a : PLATFORM can be either HIFI4 or Cortex-M7
- Lib/VIT.h : file describing VIT public API
- Lib/VIT_Model.h : file containing VIT model description for the WakeWord and Voice Commands Engines
- VIT_Voice_Commands.h : file listing the commands supported by the VIT library
- Lib/Inc : folder integrating additional VIT public interface definitions
- ExApp/VIT_ExApp.c : VIT Integration example

4 Public interfaces description

4.1 Header files

4.1.1 VIT.h

VIT.h describes all the definitions required for VIT configuration and usage:

- Detection status enumerator



- Neural Network Model strategy enumerator
- Instance parameters structure
- Control parameters structure
- Status parameters structure
- All Vit public functions

4.1.2 VIT_Model.h

VIT_Model.h contains the Model array.

The VIT_Model array can be stored in ROM (Flash) or in RAM.

- If the Model is stored in flash, VIT will make the necessary memory reservation to copy part of the Model in RAM before using it : current Cortex-M7 case.
- If the Model is stored in RAM, VIT will use directly the model from its original memory location. : HIFI4 case.

4.1.3 PL_platformTypes_CortexM7.h

PL_platformTypes_CortexM7.h describes the dedicated platform definition for VIT library.

4.1.4 PL_platformTypes_HIFI4.h

PL_platformTypes_HIFI4.h describes the dedicated platform definition for VIT library.

4.1.5 PL_memoryRegion.h

PL_memoryRegion.h describes all the memories definition dedicated to the VIT handle allocation.

4.2 Public APIs

The VIT library present different public functions to control and exercise the library:

- VIT_SetModel
- VIT_GetMemoryTable
- VIT_GetInstanceHandle
- VIT_SetControlParameters
- VIT_Process
- VIT_GetVoiceCommandFound
- VIT_GetModelInfo (subsidiary interface)
- VIT_ResetInstance (subsidiary interface)



- VIT_GetControlParameters (subsidiary interface)
- VIT_GetStatusParameters (subsidiary interface)

For detailed description of the different APIs (Parameters, return values, usage...) – Please refer to the VIT.h file.

4.2.1 Main APIs

The Main VIT APIs has to be called (in the right sequence) in order to instantiate, control and exercise VIT algorithms.

4.2.1.1 VIT_SetModel

VIT_ReturnStatus_en VIT_SetModel (PL_UINT8* pVITModelGroup)

4.2.1.1.1 Goal:

Save the address of the VIT Model and check whether the Model provided is supported by the VIT library.

4.2.1.1.2 Input parameters:

The address of the VIT Model in ROM.

4.2.1.1.3 Output parameters:

None

4.2.1.1.4 Return value:

A value of type PL_ReturnStatus_en.

If PL_SUCCESS is returned, then:

- VIT Model ROM address is saved
- VIT Model is supported by the VIT library

4.2.1.2 VIT_GetMemoryTable

VIT_ReturnStatus_en VIT_GetMemoryTable(VIT_Handle_t phInstance,
PL_MemoryTable_st *pMemoryTable,
VIT_InstanceParams_st *pInstanceParams);

4.2.1.2.1 Goal:

Goal is to inform the SW application about the required memory needed by the VIT library.

4 kinds of memory are identified:

- Fast data
- Slow data



- Fast coefficient
- Temporary or scratch

4.2.1.2.2 Input parameters:

- 1- A pointer to an instance of VIT. It must be a Null pointer as instance is not reserved yet.
- 2- A pointer to a memory table structure.
- 3- The instance parameter of the VIT library.

4.2.1.2.2.1 Output parameters:

The memory table structure is filled. It informs about the memory size required for each memory type.

4.2.1.2.3 Return value:

A value of type `PL_ReturnStatus_en`.

If `PL_SUCCESS` is returned, then VIT is succeeding to get memory requirement of

- Each sub module
- The VIT Model

4.2.1.3 *VIT_GetInstanceHandle*

```
VIT_ReturnStatus_en VIT_GetInstanceHandle(VIT_Handle_t      *phInstance,  
                                           PL_MemoryTable_st *pMemoryTable,  
                                           VIT_InstanceParams_st *pInstanceParams );
```

4.2.1.3.1 Goal:

Goal is to set and initialize the instance of VIT before processing call.
All memory is mapped to the required buffer of each sub module.

4.2.1.3.2 Input parameters:

- 1- Pointer to the future instance of VIT.
- 2- A pointer to the memory table structure. Memory allocation must be done and memory address per memory type has been saved in the table.
- 3- The instance parameter of the VIT library.
Depending the value of the instance parameter, sub module initialization is different.

4.2.1.3.3 Output parameters:

Address of the VIT instance is set.



4.2.1.3.4 Return value:

A value of type `PL_ReturnStatus_en`.

If `PL_SUCCESS` is returned, then:

- VIT instance has been set and initialize correctly
- VIT Model layers are copied in dedicated memory.

4.2.1.4 *VIT_SetControlParameters*

```
VIT_ReturnStatus_en VIT_SetControlParameters(VIT_Handle_t          phInstance,  
                                              const VIT_ControlParams_st *const pNewParams);
```

4.2.1.4.1 Goal:

Set or modify the control parameter of VIT instance. The New parameters won't be set immediately. Indeed, to avoid processing artifact due to the new parameters themselves the update sequence is under internal processing condition and will occur as soon as possible.

4.2.1.4.2 Input parameters:

- 1- VIT Handle
- 2- Pointer to a control parameter structure

Operating mode supported : `VIT_ALL_MODULE_ENABLE` ou `VIT_WAKEWORD_MODULE_ENABLE`

4.2.1.4.3 Output parameters:

None

4.2.1.4.4 Return value:

A value of type `PL_ReturnStatus_en`.

If `PL_SUCCESS` then control parameter structure has been considered and will be effective as soon as possible.

4.2.1.5 *VIT_Process*

```
VIT_ReturnStatus_en VIT_Process ( VIT_Handle_t          phInstance,  
                                  VIT_DataIn_st          *pVIT_InputBuffers,  
                                  VIT_DetectionStatus_en *pVIT_DetectionResults  
                                  );
```



4.2.1.5.1 Goal:

Analyse the audio flow to detect a “Hot Word” or a Voice command.

4.2.1.5.2 Input parameters:

- 1- VIT Handle
- 2- Temporal audio samples (160 samples @16kHz – 16-bit data)

4.2.1.5.3 Output parameters:

Detection status can have 3 different states:

- VIT_NO_DETECTION : No detection
- VIT_WW_DETECTED : WakeWord has been detected
- VIT_VC_DETECTED: a Voice Command has been detected

When VIT_WW_DETECTED is returned – VIT will switch in a Voice commands detection phase for ~3s.

When VIT_VC_DETECTED is returned – VIT_GetVoiceCommandFound() shall be called to know which command has been detected.

VIT_VC_DETECTED is also indicating the end of the Voice command research period and the switch to a WakeWord detection phase until the WakeWord is detected again. See Appendix section for further details.

4.2.1.5.4 Return value:

A value of type PL_ReturnStatus_en.

If PL_SUCCESS then the process of the new audio frame has successfully been done.

4.2.1.6 VIT_GetVoiceCommandFound

VIT_ReturnStatus_en VIT_GetVoiceCommandFound (VIT_Handle_t pVIT_Instance,
VIT_VoiceCommands_t *pVoiceCommand);

4.2.1.6.1 Goal:

Retrieve the command ID and name (when present) detected by VIT.

The function shall be called only when VIT_Process() is informing that a Voice Command has been detected (*pVIT_DetectionResults==VIT_VC_DETECTED)

4.2.1.6.2 Input parameters:

- 1- VIT Handle
- 2- Pointer to a Voice Commands struct type

4.2.1.6.3 Output parameters:

pVoiceCommand will be filled with the ID and name of the command detected.



A “UNKNOWN” command is returned if VIT does not identify any targeted command during the voice command detection phase.

4.2.1.6.4 Return value:

A value of type PL_ReturnStatus_en. If PL_SUCCESS then pVoiceCommand can be considered.

4.2.2 Secondary APIs

The secondary VIT APIs are not mandatory for good usage of VIT algorithms. They can be used in order to reset VIT in case of discontinuity in the audio recording flow (see VIT_ResetInstance description), get information on the VIT Model and get information on the internal state of VIT.

4.2.2.1 VIT_GetModelInfo

VIT_ReturnStatus_en VIT_GetModelInfo (VIT_Model_Info_t *pModel_Info)

4.2.2.1.1 Goal:

This function returns different information of the VIT model registered within VIT lib. The function shall be called only when VIT_SetModel() is informing that the model is correct. (ReturnStatus == VIT_SUCCESS).

4.2.2.1.2 Input parameters:

- 1- Pointer to a VIT_Model_Info structure

4.2.2.1.3 Output parameters:

VIT_Model_Info will be filled with the details on VIT_Model.
See VIT.h for further information.

4.2.2.1.4 Return value:

A value of type PL_ReturnStatus_en. If PL_SUCCESS then *pModel_Info can be considered.

4.2.2.2 VIT_ResetInstance

VIT_ReturnStatus_en VIT_ResetInstance(VIT_Handle_t phInstance);



4.2.2.2.1 Goal:

Reset the instance of VIT with instance parameters saved while VIT_GetInstanceHandle called. The reset doesn't take effect immediately. Indeed, to avoid processing artifact due to the reset itself the reset sequence is under internal processing condition and will occur as soon as possible.

The VIT_ResetInstance function should be called whenever there is a discontinuity in the input audio stream. A discontinuity means that the current block of samples is not contiguous with the previous block of samples.

Examples are

- Calling the VIT process function after a period of inactivity
- Buffer underrun or overflow in the audio driver

After resetting VIT Instance, VIT shall be reconfigured (call to VIT_SetControlParameters()) before continuing the VIT detection process (i.e VIT_Process()).

4.2.2.2.2 Input parameters:

VIT Handle

4.2.2.2.3 Output parameters:

None

4.2.2.2.4 Return value:

A value of type PL_ReturnStatus_en.

If PL_SUCCESS then the reset has been considered and will be effective as soon as possible.

4.2.2.3 VIT_GetControlParameters

```
VIT_ReturnStatus_en VIT_GetControlParameters(VIT_Handle_t      *phInstance,  
                                              VIT_ControlParams_st *pControlParams);
```

4.2.2.3.1 Goal:

Get the current control parameter of VIT instance.

4.2.2.3.2 Input parameters:

- 1- VIT Handle
- 2- Pointer to a control parameter structure

4.2.2.3.3 Output parameters:

Parameter structure is updated



4.2.2.3.4 Return value:

A value of type PL_ReturnStatus_en.

If PL_SUCCESS then parameter structure has been updated correctly

4.2.2.4 *GET_StatusParameters*

```
VIT_ReturnStatus_en VIT_GetStatusParameters( VIT_Handle_t      phInstance,  
                                              VIT_StatusParams_st *pStatusParams);
```

4.2.2.4.1 Goal:

Get the status parameters of the VIT library.

4.2.2.4.2 Input parameters:

- 1- VIT Handle
- 2- Pointer to a status parameter buffer

4.2.2.4.3 Output parameters:


Fill the status parameter structure.

4.2.2.4.4 Return value:

A value of type PL_ReturnStatus_en.

If PL_SUCCESS then the status parameters are valid and can be considered.

4.3 Programming sequence





4.4 Code Sample

The code sample below aimed to explain the configuration and usage of the main VIT interfaces. See ExApp.c for further details.

4.4.1 Initialization phase

Initialization sequence permit to set an instance of VIT. After initialization sequence, VIT is ready to process audio data. Initialization sequence is in the application code and must respect the following order:

1- Local variable declaration:

```
VIT_Handle_t      VITHandle;           // VIT handle pointer
VIT_InstanceParams_st VITInstParams;    // VIT instance parameters structure
VIT_ControlParams_st VITControlParams;  // VIT control parameters structure
PL_MemoryTable_st VITMemoryTable;       // VIT memory table descriptor
PL_ReturnStatus_en Status;              // status of the function
VIT_VoiceCommands_t VoiceCommand;
VIT_DetectionStatus_en VIT_DetectionResults = VIT_NO_DETECTION; // VIT detection result
VIT_DataIn_st VIT_InputBuffers = { PL_NULL, PL_NULL, PL_NULL };
```

2- Set the instance parameters:

Software application code set the instance parameters of VIT function

As an example:

```
VITInstParams.SampleRate_Hz    = VIT_SAMPLE_RATE;
VITInstParams.SamplesPerFrame = VIT_SAMPLES_PER_FRAME;
VITInstParams.NumberOfChannel = _1CHAN;
```

3- Set model address:

```
Status = VIT_SetModel(VIT_Model); // Pass the address of the VIT Model
```

4- Get memory size and location requirement:

```
Status = VIT_GetMemoryTable(PL_NULL,
                             &VITMemoryTable,
                             &VITInstParams);
```

5- Reserve memory space:

Based on the VITMemoryTable informations, the software application reserve memory space in the required memory type. The start address of each memory type is saved in VITMemoryTable structure.

```
#define MEMORY_ALIGNMENT 4
```




```

//Following pseudo code applied to MemType =
//PL_MEMREGION_PERSISTENT_SLOW_DATA, PL_MEMREGION_PERSISTENT_COEF and
//PL_MEMREGION_TEMPORARY
if (VITMemoryTable.Region[MemType].Size != 0)
{
    pMemory = malloc_in_SLOW_MEMORY (VITMemoryTable.Region[MemType].Size +
        MEMORY_ALIGNMENT);
    VITMemoryTable.Region[MemType].pBaseAddress = (void *) pMemory;
}

//Following pseudo code applied to MemType = PL_MEMREGION_PERSISTENT_FAST_DATA
if (VITMemoryTable.Region[MemType].Size != 0)
{
    pMemory = malloc_in_FAST_MEMORY (VITMemoryTable.Region[MemType].Size +
        MEMORY_ALIGNMENT);
    VITMemoryTable.Region[MemType].pBaseAddress = (void *) pMemory;
}
}

```

6- Get instance of VIT:

```

VITHandle = PL_NULL; // force to null address for correct initialization
Status = VIT_GetInstanceHandle(    &VITHandle,
                                   &VITMemoryTable,
                                   &VITInstParams);

```

7- Set control parameters:

SW application code set the new control parameters and call VIT_SetControlParameters:

```

VITControlParams.OperatingMode = VIT_ALL_MODULE_ENABLE;
Status = VIT_SetControlParameters(VITHandle,
                                   &VITControlParams);

```

4.4.2 Process phase

For each new input audio frame, VIT_Process is called by the application code.

```

VIT_InputBuffers.pBuffer_Chan1 = Audio_Buffer; //temporal data(10ms @16khz mono 16-bit)
VIT_InputBuffers.pBuffer_Chan2 = PL_NULL;
VIT_InputBuffers.pBuffer_Chan3 = PL_NULL;

Status = VIT_Process( VITHandle,
                     &VIT_InputBuffers,
                     &VIT_DetectionResults ); // VIT detection results

```

Check status of the detection:



```

if (VIT_DetectionResults == VIT_WW_DETECTED)
{
    // WakeWord detected - possible action :
    printf("WakeWord detected \n");
}
else if (VIT_DetectionResults == VIT_VC_DETECTED)
{
    // a Voice Command detected - Retrieve command information :
    Status = VIT_GetVoiceCommandFound(VITHandle, &VoiceCommand);
    printf("Voice Command : %d detected \n", VoiceCommand.Cmd_Id);

    // Retrieve CMD name : OPTIONAL
    // Check first if CMD string is present
    if (VoiceCommand.Cmd_Name != PL_NULL)
    {
        printf(" %s\n", VoiceCommand.Cmd_Name);
    }
}
else
{
    // No specific action since VIT did not detect anything for this frame
}

```

4.4.3 Delete phase

The framework can delete the environment process/task of VIT with stopping calling VIT_Process. There is no specific VIT APIs in order to free VIT internal memory since the memory allocation is owned by the framework itself (no internal memory allocation).

The framework will have to free the memory associated with the different VIT memoryTables. If the framework did not save the MemoryTables properties, VIT_GetMemoryTable can be called with VITHandle in order to retrieve base addresses and size of the different MemoryTables.

```

Status = VIT_GetMemoryTable(VITHandle,
                            &VITMemoryTable,
                            &VITInstParams);

// Free memory
for (i = 0; i < PL_NR_MEMORY_REGIONS; i++)
{
    if (VITMemoryTable.Region[i].Size != 0)
    {
        free((PL_INT8 *)VITMemoryTable.Region[i].pBaseAddress);
    }
}

```



```
}
```

4.4.4 Additional code snippet (secondary APIs)

- VIT_GetStatusParameters

```
VIT_StatusParams_st VIT_StatusParams_Buffer;  
VIT_StatusParams_st* pVIT_StatusParam_Buffer = (VIT_StatusParams_st*)&VIT_StatusParams_Buffer;  
  
VIT_GetStatusParameters(VITHandle, pVIT_StatusParam_Buffer, sizeof(VIT_StatusParams_Buffer));  
printf("\nVIT Status Params\n");  
printf(" VIT LIB Release = 0x%04x\n", pVIT_StatusParam_Buffer->VIT_LIB_Release);  
printf(" VIT Model Release = 0x%04x\n", pVIT_StatusParam_Buffer->VIT_MODEL_Release);
```



5 VIT Profiling

Cortex-M7 :

MHz	Memory (kB)					
260*	ROM		RAM			
	Data	Code	FAST	SLOW	SCRATCH	Total
	637	45	411	177	12.7	600.7

*with FAST memory buffer (PL_MEMREGION_PERSISTENT_FAST_DATA) allocated in DTC

Figure 2 - VIT profiling figures on RT1060 platform

VIT Stack usage < 1kB


6 Appendix

The example below is illustrating the voice command research window : end of Voice Command utterance shall occur in a ~3s window from the wake word.

Example 1 :

The voice command utterance is ending 1.7s after the WakeWord :

After having detected the WakeWord, VIT will switch to the Voice Command research mode. VIT will detect the Voice command, and switch back to the Wake word detection mode.




Example 2:

The voice command utterance is ending 3s after the WakeWord :

After having detected the WakeWord, VIT will switch to the Voice Command research mode. VIT will not be able to detect the Voice command, since the Command is not fitting in the 3s window.

At the end of the 3s research window, VIT will return an “UNKNOWN” command and switch back to the WakeWord detection mode.





How to Reach Us:

Home Page:

nxp.com

Web Support:

nxp.com/support

Information in this document is provided solely to enable system and software implementers to use NXP products. There are no express or implied copyright licenses granted hereunder to design or fabricate any integrated circuits based on the information in this document.

NXP reserves the right to make changes without further notice to any products herein. NXP makes no warranty, representation, or guarantee regarding the suitability of its products for any particular purpose, nor does NXP assume any liability arising out of the application or use of any product or circuit, and specifically disclaims any and all liability, including without limitation consequential or incidental damages. “Typical” parameters that may be provided in NXP data sheets and/or specifications can and do vary in different applications, and actual performance may vary over time. All operating parameters, including “typicals,” must be validated for each customer application by customer’s technical experts. NXP does not convey any license under its patent rights nor the rights of others. NXP sells products pursuant to standard terms and conditions of sale, which can be found at the following address: nxp.com/SalesTermsandConditions.

NXP, the NXP logo, Freescale, and the Freescale logo are trademarks of NXP B.V. All other product or service names are the property of their respective owners. All rights reserved.

© 2018-2019 NXP B.V.